



SETTING THE BOM QUANTITY

WHAT WE WILL LEARN

We will learn about ways of setting the BOM quantity using object dependencies.

THESE ARE THE KEY POINTS

- Characteristics that reference Master Data Fields
- Using Variant Tables to store BOM Quantity Values
- Procedure to GET the Bom Quantity from Variant Table
- Allocate Procedure GET to Configuration Profile
- Procedure to SET Bom Quantity
- Allocate Procedure SET to KMAT Bom item

HERE IS THE DETAIL

Often we want to set the BOM quantity, or for that matter other data fields in the BOM or the routing, and even in some cases the sales order.

This lesson will show the fundamental steps to do this.

First we need to start with creating a special characteristic. Use CT04 and create STPO_MENGE maintain reference to table as shown



Create another characteristic as numerical BOX_COLOUR_BOM_QTY. Assign this to A300_BOX class with CL02. This will store the BOM Qty to be passed to the Bom

Use CU61 - Create a Variant table with characteristics BOX_SIZE and BOX_COLOUR_BOM_QTY. Make BOX_SIZE the key

Maintain Table Values with CU60. Set different values for each Box Size.

Use CU01 to create procedures.

Procedures are used to set values. The first procedure gets the values from the table and stores it. The second procedure reads the stored value and sets it in the BOM.

PR_COLOUR_QTY_GET

```
000010 Table VT_COLOUR_QTY
000020 (BOX_SIZE = BOX_SIZE,
000030 BOX_COLOUR_BOM_QTY = $self.BOX_COLOUR_BOM_QTY)
```

Assign to Configuration Profile

PR_COLOUR_QTY_SET

```
000010 $self.STPO_MENGE = BOX_COLOUR_BOM_QTY
```

Assign to BOM Item

Test the result in CU50.

WANT TO SEE THE DEMO'S

Setting the BOM Quantity

PLAY